

Configure Realm Routing Table

OPERATING INSTRUCTIONS

Copyright

© Ericsson AB 2015–2017. All rights reserved. No part of this document may be reproduced in any form without the written permission of the copyright owner.

Disclaimer

The contents of this document are subject to revision without notice due to continued progress in methodology, design and manufacturing. Ericsson shall have no liability for any error or damage of any kind resulting from the use of this document.

Trademark List

All trademarks mentioned herein are the property of their respective owners. These are shown in the document Trademark Information.



Contents

1	Description	1
2	Procedure	1
2.1	Configure Realm Routing Table	1





1 Description

This instruction describes how to configure a Realm Routing Table (RRT) in the Diameter application for the following:

- Authorization and Authentication Application Routing
- Accounting Application Routing

The RRT contains routing information, which is used to decide how to process the incoming requests from a particular Diameter application.

The RRT must be configured for the following traffic cases:

- When outgoing messages are sent to the realm
- When the destination host is not specified
- When the destination host is specified, but not present in peer table, that is, among the configured neighbor peers

2 Procedure

2.1 Configure Realm Routing Table

Prerequisites

- No documents are required.
- No tools are required.
- The following conditions must apply:
 - For configuration of Authorization and Authentication Application Routing, the appropriate routing information is known.
 - For configuration of Accounting Application Routing, the appropriate routing information is known.
 - An Ericsson Command-Line Interface (ECLI) session in Exec mode is in progress.

Steps

1. Navigate to the *DIA-CFG-RoutingContainer* Managed Object (MO), for example:



```
>dn ManagedElement=NODE06ST,XYZFunction=xyz,DIA-CFG-Application=DIA,DIA-CFG-StackContainer=abc,DIA-CFG-RoutingContainer=abc
```

2. Enter Config mode:

```
(DIA-CFG-RoutingContainer=abc) >configure
```

3. Create a *DIA-CFG-Drt* MO, for example:

```
(config-DIA-CFG-RoutingContainer=abc) >DIA-CFG-Drt=ericsson.com:abc:FALSE
```

4. Commit the settings:

```
(config-DIA-CFG-Drt=ericsson.com:abc:FALSE) >commit
```

5. Navigate to the *DIA-CFG-RoutingContainer* MO:

```
(DIA-CFG-Drt=ericsson.com:abc:FALSE) >up
```

6. Show the settings:

```
(DIA-CFG-RoutingContainer=abc) >show DIA-CFG-Drt=ericsson.com:abc:FALSE
```

The following is an example output:

```
DIA-CFG-Drt=ericsson.com:abc:FALSE
DIA-CFG-AccReqContainer=accReqContainerName
DIA-CFG-AuthReqContainer=authReqContainerName
```

7. Is it required to configure Accounting Application Routing?

- Yes: Continue with the next step.
- No: Proceed with Step 17.

8. Navigate to the *DIA-CFG-AccReqContainer* MO, for example:

```
(DIA-CFG-RoutingContainer=abc) >dn ManagedElement=NODE06ST,XYZFunction=xyz,DIA-CFG-Application=DIA,DIA-CFG-StackContainer=abc,DIA-CFG-RoutingContainer=abc,DIA-CFG-Drt=ericsson.com:abc:FALSE,DIA-CFG-AccReqContainer=accReqContainerName
```

9. Enter Config mode:

```
(DIA-CFG-AccReqContainer=accReqContainerName) >configure
```

10. Create a *DIA-CFG-AppRouting* MO, for example:

```
(config-DIA-CFG-AccReqContainer=accReqContainerName) >DIA-CFG-AppRouting=0:8
```



11. Set attribute `action`, for example:

```
(config-DIA-CFG-AppRouting=0:8) >action=4
```

12. Set attribute `nodeIds`, for example:

```
(config-DIA-CFG-AppRouting=0:8) >nodeIds="0:node12.ericsson.com#abc"
```

13. Set the optional attributes, as needed:

- `autoFailback`
- `secondaryNodeIds`

14. Commit the settings:

```
(config-DIA-CFG-AppRouting=0:8) >commit
```

15. Verify the settings:

```
(DIA-CFG-AppRouting=0:8) >show
```

The following is an example output:

```
DIA-CFG-AppRouting=0:8
  action="4"
  nodeIds
    "0:node12.ericsson.com#abc"
  secFailoverActive=false
```

16. Is it required to configure the Authorization and Authentication Application Routing?

- Yes: Continue with the next step.
- No: Proceed with Step 25.

17. Navigate to the *DIA-CFG-AuthReqContainer* MO:

```
>dn ManagedElement=NODE06ST,XYZFunction=xyz,DIA-CFG-Applicat  
ion=DIA,DIA-CFG-StackContainer=abc,DIA-CFG-Routing  
Container=abc,DIA-CFG-Drt=ericsson.com:abc:FALSE,DIA-CF  
G-AuthReqContainer=authReqContainerName
```

18. Enter Config mode:

```
(DIA-CFG-AuthReqContainer=authReqContainerName) >config  
ure
```

19. Create a *DIA-CFG-AppRouting* MO, for example:

```
(config-DIA-CFG-AuthReqContainer=authReqContainerName) >DIA-CFG-AppRouting=0:8
```



20. Set attribute `action`, for example:

```
(config-DIA-CFG-AppRouting=0:8) > action=4
```

21. Set attribute `nodeIds`, for example:

```
(config-DIA-CFG-AppRouting=0:8) > nodeIds="0:node12.ericsson.com#abc"
```

22. Set the optional attributes, as needed:

- `autoFailback`
- `secondaryNodeIds`

23. Commit the settings:

```
(config-DIA-CFG-AppRouting=0:8) > commit
```

24. Verify the settings:

```
(DIA-CFG-AppRouting=0:8) > show
```

The following is an example output:

```
DIA-CFG-AppRouting=0:8
  action="4"
  nodeIds
    "0:node12.ericsson.com#abc"
  secFailoverActive=false
```

25. Navigate to the relevant `DIA-CFG-RoutingContainer` MO, for example:

```
> dn ManagedElement=NODE06ST,XYZFunction=xyz,DIA-CFG-Application=DIA,DIA-CFG-StackContainer=abc,DIA-CFG-RoutingContainer=abc
```

26. Verify the settings:

```
(DIA-CFG-RoutingContainer=abc) > show -r
```

The following is an example output:



```
DIA-CFG-RoutingContainer=abc
  routingContainerName="routingContainerName"
DIA-CFG-Drt=ericsson.com:abc:FALSE
  DIA-CFG-AccReqContainer=accReqContainerName
DIA-CFG-AppRouting=0:8
  action="4"
  nodeIds
    "0:node12.ericsson.com#abc"
  secFailoverActive=false
DIA-CFG-AuthReqContainer=authReqContainerName
DIA-CFG-AppRouting=0:8
  action="4"
  nodeIds
    "0:node12.ericsson.com#abc"
  secFailoverActive=false
```