

Licensing, License Manager Not Available

Ericsson Centralized User Database

OPERATING INSTRUCTION

Copyright

© Ericsson AB 2016. All rights reserved. No part of this document may be reproduced in any form without the written permission of the copyright owner.

Disclaimer

The contents of this document are subject to revision without notice due to continued progress in methodology, design and manufacturing. Ericsson shall have no liability for any error or damage of any kind resulting from the use of this document.

Trademark List

All trademarks mentioned herein are the property of their respective owners. These are shown in the document Trademark Information.



Contents

1	Introduction	1
1.1	Alarm Description	1
1.2	Prerequisites	2
2	Procedure	3
	Glossary	5
	Reference List	7



Licensing, License Manager Not Available



1 Introduction

This instruction concerns alarm handling for the Licensing, License Manager Not Available alarm.

1.1 Alarm Description

This alarm is raised in the following situations:

- The CUDB application cannot connect to the License Manager (LM).
- Registration to the LM failed.

The possible alarm causes and the corresponding fault reasons, fault locations, and impacts are described in Table 1.

Table 1 Alarm Causes

Alarm Cause	Description	Fault Reason	Fault Location	Impact
CUDB cannot contact or register to the LM.	LM not available	There is a problem with the LM servers (for example server crash(es)).	LM	Configuration changes subject to licensing will not be accepted.

The alarm attributes are listed and explained in Table 2.

Table 2 Alarm Attributes

Attribute Name	Attribute Value
Auto Cease	No
Module	LICENSING
Error Code	1
Timestamp First	Date and time when the alarm was raised for the first time.
Repeated Counter	Number which indicates how many times the alarm was raised.
Timestamp Last	Date and time of the most recent alarm raise.
Resource ID	1.3.6.1.4.1.193.169.14.2.1
Alarm Model Description	License Management, Licensing
Alarm Active Description	License manager not available
ITU Alarm Event Type	qualityOfServiceAlarm (3)
ITU Alarm Probable Cause	softwareProgramError (546)
ITU Alarm Perceived Severity	Major (4)
Originating source IP	Node IP where the alarm was raised.
Sequence Number	Number which indicates the order in which the alarms are raised.



The following is the consequence for the node if the alarm is not solved:

- Configuration changes subject to licensing will not be accepted until the fingerprint parameter is correctly set up, and the LM server becomes operational.

For further information about attribute descriptions, refer to [CUDB Node Fault Management Configuration Guide, Reference \[1\]](#).

1.2 Prerequisites

This section provides information on the documents, tools, and conditions that apply to the procedure.

1.2.1 Documents

Before starting this procedure, ensure that you have read the following documents:

- [CUDB Node Fault Management Configuration Guide, Reference \[1\]](#), regarding alarm configuration.
- [System Safety Information, Reference \[3\]](#)
- [Personal Health and Safety Information, Reference \[4\]](#)

1.2.2 Tools

Not applicable.

1.2.3 Conditions

Not applicable.



2 Procedure

Do the following:

1. Check if the COM SA, AMF SI Unassigned alarm is raised for the LM. If the alarm is raised, then follow the procedure in COM SA, AMF SI Unassigned, Reference [5]. After that, proceed to Step 2.
2. Execute the following command:

```
cudbHaState | grep Lm
```

The expected output must be similar to the following example:

```
saAmfSISUHASState."safSu=LmSa-Su-1,safSg=LmSa-Sg,safApp=ERIC-LmS  
a-App"."safSi=LmSa-Si": active(1)  
saAmfSISUHASState."safSu=LmSa-Su-0,safSg=LmSa-Sg,safApp=ERIC-LmS  
a-App"."safSi=LmSa-Si": standby(2)
```

If the states listed in the output are not active or standby, then contact the next level of support. If the output is similar to the above example, then continue with the next step.

3. Clear the alarm manually as described in the “Clearing Alarms” section of CUDB Node Fault Management Configuration Guide, Reference [1].



Licensing, License Manager Not Available



Glossary

For the terms, definitions, acronyms and abbreviations used in this document, refer to [CUDB Glossary of Terms and Acronyms](#), Reference [2].



Licensing, License Manager Not Available



Reference List

CUDB Documents

- [1] CUDB Node Fault Management Configuration Guide
- [2] CUDB Glossary of Terms and Acronyms

Other Ericsson Documents

- [3] System Safety Information
- [4] Personal Health and Safety Information
- [5] COM SA, AMF SI Unassigned