


CCO

CCO

- Use the CCO menu to query SMUs, Service Packs, and Release Software files and information for various IOS XR platforms and releases.
- To exclude certain platforms and releases from displaying under the CCO menu, go to Tools – User Preferences and select the releases you want to exclude.



CCO

- To download files, select the files and click Action – Download to Server Repository. The selected files will first be downloaded to the CSM Server internal repository, then uploaded to the use-selected server repository. A green check icon is displayed in the Status column if the file exists in the CSM Server internal repository (i.e. csm_data/repository).
- The Optimal filter removes superseded SMUs and Service Packs.
- The yellow highlights indicate the files have been posted within the last 7 days.

ASR9K-PX-5.3.3 > SMUs 54 Service Packs 1 Release Software 4

100 records per page

Optimal

Action

Download to Server Repository

Export Software Information

| <input type="checkbox"/> | Status | Posted Date | SMU ID | DDTS | Type | Description | Impact |
|--------------------------|--------|-------------|-------------------------|----------------------------|----------|--|-------------|
| <input type="checkbox"/> | ⚠ | 07/05/2016 | AA11677 | CSCuz01862 | Optional | Juggernaut V7 SW support for new FPDs imux-1.4, emux-1.4 and cgmack-41 | Hitless |
| <input type="checkbox"/> | ⚠ | 07/05/2016 | AA11677 | CSCuz01862 | Optional | aipc_proxy process crash in 6.1.1.04I.DT_IMAGE | Needs Re |
| <input type="checkbox"/> | ✓ | 07/01/2016 | AA11562 | CSCuy08198 | Optional | fab_vqi_alloc crash on multiple reloads of megatron full box | Needs Re |
| <input type="checkbox"/> | ⚠ | 06/29/2016 | AA11686 | CS | Optional | Fib_mgr process crash due to 'not enough memory' | Needs Re |
| <input type="checkbox"/> | ⚠ | 06/28/2016 | AA11487 | CSCuz71647 | Optional | BGP Umbrella SMU | Traffic Los |

Export Software information

- To export software information, click Action – Export Software Information. Supported export formats are HTML and Microsoft Excel. Click OK to export the information to a file.

Export Software Information

Export Format

Microsoft Excel

Layout

Concise

OK

Cancel